

FUJITSU Software BS2000 ROBAR-CL

Version 7.7A
June 2021

Release Notice

All rights reserved, including intellectual property rights.
Technical data subject to modifications and delivery subject to availability. Any liability that the data and illustrations are complete, actual or correct is excluded. Designations may be trademarks and/or copyrights of the respective manufacturer, the use of which by third parties for their own purposes may infringe the rights of such owner.

Copyright © 2021 Fujitsu Technology Solutions GmbH

Fujitsu and the Fujitsu logo are trademarks or registered trademarks of Fujitsu Limited in Japan and other countries. BS2000 is a trademark of Fujitsu Technology Solutions GmbH in Germany and other countries.

Release Notice ROBAR-CL V7.7A

1 General	3
1.1 Ordering	3
1.2 Delivery	3
1.3 Documentation	4
2 Software extensions	5
3 Technical information	5
3.1 Resource requirements	5
3.2 Software configuration	5
3.2.1 Necessary environment	5
3.2.2 Coexistence with MAREN	5
3.3 Product installation	6
3.4 Product use	6
3.5 Discontinued functions	7
3.6 Incompatibilities	7
3.7 Restrictions	7
3.8 Procedure in case of errors	7
4 Hardware support	8

1 General

This Release Notice contains a summary of the major expansions, interdependencies and application notes pertaining to ROBAR-CL V7.6A running under the operating system BS2000.

The release level is that of June 2021.

Customers will receive an updated version of this file if any subsequent changes were made.

The Release Notice belongs to the delivery scope of this product.

This and other Release Notice(s) are contained on the SoftBooks-DVD and are available online at <https://bs2manuals.ts.fujitsu.com>

ROBAR consists of the two components ROBAR-CL (ROBAR client, local BS2000 part) and ROBAR-SV (central Linux part).

For ROBAR-SV, refer to the Release Notice ROBAR-SV.

1.1 Ordering

ROBAR-CL can be order from your local distributors.

ROBAR-CL is subject to the general terms and conditions of the software product use and service agreement.

1.2 Delivery

The files for ROBAR-CL are deliver via SOLIS.

Current file and volume characteristics are list in the SOLIS delivery cover letter.

Delivery of ROBAR-CL includes the following files:

SYSMES.ROBAR-CL.076	Message file
SYSPAR.ROBAR-CL.076.MESSAGES	ROBAR relevant system messages
SYSPAR.ROBAR-CL.076.PROZPARAM	Parameter file
SYSPAR.ROBAR-CL.076.TEXT.D	Application own usage, German
SYSPAR.ROBAR-CL.076.TEXT.E	Application own usage, English
SYSPRC.ROBAR-CL.076	Start procedure ROBAR-CL in BS2000
SYSPRC.ROBAR-CL.076.MAREN	Get information from MAREN catalogue
SYSPRG.ROBAR-CL.076.DCAM	ROBAR-DCAM application
SYSPRG.ROBAR-CL.076.SDF	ROBAR-SDF application
SYSDF.ROBAR-CL.076	System syntax file
SYSSII.ROBAR-CL.076.	Structure and installation information file

1.3 Documentation

The manual for ROBAR is
ROBAR V7.7 Controlling MTC Archive Systems.

The documentation is also available in the form of online manuals at

<https://bs2manuals.ts.fujitsu.com>

2 Software extensions

The extensions only affect ROBAR-SV V7.7A. The extensions are describe in the relevant release notice.

3 Technical information

3.1 Resource requirements

1. Virtual address space
Negligible
2. Static disc space
Up to the maximum of 2 MBytes
3. Dynamic disc space
Up to the maximum of 4 MBytes (depends on the stored trace files)
4. Special hardware/firmware/processor type/Real memory
Not relevant.

3.2 Software configuration

3.2.1 Necessary environment

1. ROBAR-SV as of V7.6A
2. As of OSD/BC V11.0

MAREN is only necessary for the locations management, tape encryption and for ETERNUS CS, optional otherwise.

3.2.2 Coexistence with MAREN

ROBAR-CL calls MAREN to update the MAREN catalogue after cartridge insertion and ejection. If MAREN version changes during the BS2000 session, ROBAR-CL must be stop and restarted.

ROBAR-CL selects the highest MAREN version available, if the system administrator did not change the version with the command SELECT-PRODUCT-VERSION.
The parameters MARENLNK and MARENREP in the ROBAR-CL start procedure are useless (Value= *NONE).

Remarks:

1. MAREN is call in ROBAR-CL-DCAM and in ROBAR-CL-SDF.
2. For EXPORT of cartridges it is recommended to issue the //EXPORT-VOLUME statement in MAREN instead of using ROBAR-CL-SDF if MAREN is used.

3.3 Product installation

Installation of the product ROBAR-CL with the installation monitor IMON is mandatory. The information concerning installation in the delivery cover letter and in the product documentation must be followed as well as the information given below.

The installation actions described as requirements in the delivery cover letter must be complete before calling IMON.

3.4 Product use

The messages "NBR0740" and "EXC0031" must not be suppressed by the "SET-MSG-SUPPRESSION" command before you start ROBAR-CL-DCAM. This can be checked with "SHOW-MSG-SUPPRESSION".

The following settings must be made with the command MODIFY-MOUNT-PARAMETER for optimum tape operation:

- (1) UNLOAD-RELEASED-TAPE= *REGARDLESS-OF-USER-REQUEST(TAPE=*MBK)

This setting is mandatory. It unloads all volumes immediately after they have been used.

- (2) NEXT-TAPE-MOUNT=*LEAST-RECENTLY-USED-DEVICE

This setting causes the reservation of devices in round robin method, so there is a load spreading.

- (3) PREMOUNT-MSG=*IGNORE-USER-REQUEST

This parameter suppresses the PREMOUNT message (NKVT012). The message is of no significance in robot operation since ROBAR just responds with 'tsn.' but does not otherwise react.

Restarting the connection between ROBAR-CL and ROBAR-SV

It may occur that the connection between ROBAR-CL and ROBAR-SV cannot be re-established after being down. The best way to restart ROBAR-CL and ROBAR-SV is to use this sequence:

- terminate the ROBAR-DCAM application on the BS2000 (command BCAPPL)
- stop ROBAR-SV
- start ROBAR-SV
- start the ROBAR-CL-DCAM application

Central MAREN system

For performance reasons, it is strongly advised to define as central MAREN system in ROBAR only the host on which the MAREN catalogue was installed. Otherwise redundant information is transferred to other hosts and would make complex updates in the MAREN catalogue.

The central MAREN system MUST be available when exporting and importing cartridges.

3.5 Discontinued functions

None

3.6 Incompatibilities

ROBAR-CL V7.7A is fully compatible with ROBAR-CL V7.6A

3.7 Restrictions

None

3.8 Procedure in case of errors

If an error occurs, the following error information is required for diagnosis:

1. Detailed description of the situation how the error can be reproduce.
2. Documents from BS2000:
CONSLOG file
ROBAR-CL trace file
File SYSRPT.ROBAR-CL.077.<DCAM-name>.<tsr>

4 Hardware support

ROBAR-CL V7.7A can be use on all business servers supported by OSD/BC V11.0 and BS2000 OS DX V1.0A

For further information about the supported tape devices for a robot system environment please refer to the release notice of BS2000 OS DX V1.0A, OSD/BC V11.0 and to ROBAR-SV V7.7A